


THERMOMARK CARD - Driver Installation - Windows XP

Connect to Phoenix Contact USA's Printer Resources


Open web browser and connect to Phoenix Contact's Printer Resources located at <http://www.phoenixcontact.com/printers>



THERMOMARK CARD - Driver Installation - Windows XP

Locate Printer


Scroll down the page until you see **Thermomark Card - 5146464** and click "Driver"



THERMOMARK CARD - Driver Installation - Windows XP

Locate Drivers

Scroll down the page until you locate the Drivers and Driver Modules section. **Do not click.**



The screenshot shows a Firefox browser window with two tabs: 'PHOENIX CONTACT | Printer Resourc...' and 'PHOENIX CONTACT | Thermal transf...'. The address bar shows the URL: <https://www.phoenixcontact.com/online/portal/us?urlile=pxc-oc-itemdetail:pid=5146464&library=usen&tab=5>. The page content includes a table of manuals and a section titled 'Drivers and Driver Modules'.

| | | | |
|--------------------------|--|---------|----|
| <input type="checkbox"/> | Manual de usuario THERMOMARK CARD um_es_thermomark_card_104612_es_02.pdf | | |
| <input type="checkbox"/> | [pdf, 4 MB] Manual Prod.-Id. 104612: UM PL THERMOMARK CARD Podrecznik uzytkownika THERMOMARK CARD um_pl_thermomark_card_104612_pl_02.pdf | Polish | 02 |
| <input type="checkbox"/> | [pdf, 4 MB] Manual Prod.-Id. 104612: UM SV THERMOMARK CARD Användarhandbok THERMOMARK CARD um_sv_thermomark_card_104612_sv_02.pdf | Swedish | 02 |

Drivers and Driver Modules

| | Description | Language | Revision |
|--------------------------|--|---------------|----------|
| <input type="checkbox"/> | [zip, 3 MB] Drivers and Driver Modules Device driver Driver_TC_TR_X1_4.6.66.zip | International | 4.6.66 |

Download Drivers to Desktop

Right-Click the [Drivers and Driver Modules](#) link and select 'Save Link As...'

NOTE: In Internet Explorer, right-click and choose 'Save Target As ...'

The screenshot shows a web page with several sections: "Drivers and Driver Modules", "Material Description", "Various", and "E-Learning". Each section contains a table with columns for "Description", "Language", and "Revision". A right-click context menu is open over a link in the "Drivers and Driver Modules" table. The menu items are: "Open Link in New Tab", "Open Link in New Window", "Open Link in New Private Window", "Bookmark This Link", "Save Link As...", "Copy Link Location", "Inspect Element (Q)", "Add to Evernote", "Clearly", "LastPass", "LastPass Fill Forms", and "Adblock Plus: Block image...". The "Save Link As..." option is highlighted, and a mouse cursor is pointing at it. Two callout boxes with numbers 1 and 2 are present: box 1 points to the link in the table, and box 2 points to the "Save Link As..." menu item.

| | Description | Language | Revision |
|--------------------------|---|---------------|----------|
| <input type="checkbox"/> | [zip, 2 MB] Drivers and Driver Modules Device driver Driver_TC_TR_X1_4.6.66.zip | International | 4.6.66 |

| | Description | Language | Revision |
|--------------------------|---|---------------|----------|
| <input type="checkbox"/> | [zip, 1 MB] Material Description Materialbeschreibung für Thermomark Material_Description_TMRoll_X1.zip | International | |


| | Description | Language | Revision |
|--------------------------|--|---------------|----------|
| <input type="checkbox"/> | [gz, 168 KB] Various Open Source patch-2.6.29.1-cabespresso.gz | International | 2.6.29.1 |

THERMOMARK CARD - Driver Installation - Windows XP

Save Driver Files Locally


Save the .zip anywhere you'd like. It's a temporary file and will be deleted after installation. Be sure to note the save location so you will be able to find the file when the download is completed.

Recommended: Locate **Desktop** under Favorites and click **Save**. The .zip file will be located directly on your desktop.




Locate and Extract Files

Locate **Driver_TC_TR_X1_4.6.66.zip** . Right-click and select **Extract All...**



Extraction Wizard


Click **Next >** to continue.



Extraction Wizard


Select a destination for the extracted files by clicking **Browse**. Then choose a location where you will be able to locate the files.

Recommended: Select Desktop to easily find the unzipped folder.



Extraction Wizard


Check the checkbox next to "Show extracted files when complete". Click **Finish**.



Open Driver Files

After the files are unpacked, a window will automatically open displaying your newly unzipped folder. Double click the folder to open.


*If a window **does not** appear, locate the original .zip file. The unzipped file will be located in the same place.*



THERMOMARK CARD - Driver Installation - Windows XP


Start Driver Installation

Within the driver folder, locate **PrnInst.exe**. Double click to start the installation wizard.




Begin Driver Installation

Click **Run** > to begin



Driver Installation

Click **Next >**




THERMOMARK CARD - Driver Installation - Windows XP

Selecting the Printer

Make sure PHOENIX CONTACT is highlighted under Manufacturers.
Select **THERMOMARK CARD** from Printers.

Click **Next >** to continue.




Printer Options

Select the port* your printer is connected to.


Click **Finish**.

**usually USB##*




Installation Complete

The installation will be complete after finishing the previous step. Close all windows and you may now drag **both** Driver_TC_TR_4.6.66 folders to the Recycle Bin.



Confirmation


To make sure your printer installed correctly, locate **Devices and Printers** on the Start Menu.



THERMOMARK CARD - Driver Installation - Windows XP

Devices and Printers


Your installation was successful if THERMOMARK CARD is listed.



Setting Up a Printer in CLIP PROJECT


To begin, open the Output Devices Setup window

1. File
2. Print setup...



Output Devices Setup


1. Select **THERMOMARK CARD** in Device Configurations
2. Click **New**



THERMOMARK CARD - Driver Installation - Windows XP

Set Up the Printer

1. Click on the drop down menu & choose the printer driver
2. Click **OK**



Installation Complete

You are now ready to print.

Thank you for using Phoenix Contact's **THERMOMARK CARD** printer!

